




Open the Statistics application.

Tap Edit, Clear All, OK.

Tap on the  icon.




Now tap  and so on to display your choice of 2, 3 or 4 lists on the screen.



Two of the settings at the bottom of the screen reflect your settings in Main – the angle mode and choice of Standard or Decimal.


Between them, make sure that Auto is displayed. Auto means that all graphs will be scaled automatically.

To turn Auto on or off tap SetGraph, Stat Window Auto and then tap On or Off.



Type a few numbers into list1.

If you make a typing mistake, tap onto the wrong number and simply re-type the correct value.





To insert an extra number, for example between the 3 and the 5 shown here, tap onto the lower of the two numbers.

Tap Edit, Insert Cell.

Undefined appears in the cell.

Now type in the extra value and tap EXE.



To delete an existing number tap onto the number.

Then either

tap Edit, Delete, Cell.

or

press the Clear button.

